LDAP_Servers

- Introduction
- How Does it Work?
- Creating a LDAP Server Entry
- View a LDAP Server Details
- Database Schema
- API / Web Access

Introduction

Open-AudIT can be configured to use LDAP servers (Microsoft Active Directory and/or OpenLDAP) to authenticate and authorize a user and in addition, to create a user account in Open-AudIT using assigned roles and orgs based on LDAP group membership.

How Does it Work?

If using Active Directory, you do not need to populate the user_dn or user_membership_attribute attributes. These are used by OpenLDAP only.

If the user logging on to Open-AudIT does not have the access to search LDAP, you can use another account which does have this access. Use the dn_ac count and dn_password to configure this.

Examples:

If you need to configure OpenLDAP access for your users and a given users access DN is normally uid=username@domain.cn=People.dc=your, dc=domain.dc=com then you should set base_dn to dc=your, dc=domain.dc=com and user_dn to uid=@username@domain.cn=People. The special words @username and @domain will be replaced by the login details provided by your user on the login page.

If you need to configure Active Directory access, you can usually use the example of cn=Users,dc=your,dc=domain,dc=com for your base_dn. here is no need to set user_dn.

These are only examples. You may need to adjust these attributes to suit your particular LDAP.

If you are using Open-AudIT Professional or Enterprise and you enable LDAP and you wish for user accounts to be automatically created at logon, you must edit the (text) file:

Linux - /usr/local/omk/conf/opCommon.nmis

Windows - c:\omk\conf\opCommon.nmis

And ensure that auth_method_1 is set to openaudit.

Creating a LDAP Server Entry

A LDAP Server can be created using the web interface if a user has a role that contains the ldap_servers::create permission. Go to menu: Admin -> Ldap Servers-> Create Ldap Server. There is also a create button on the collection page.



📱 Open-Aulf Erforgenius 338 View - Discover - Report - Manage - 🕹 Unar Andrée - Liberra en et de la Constance - 🛓 Unar Andrée - Liberra en et de la Constance - Liberra en et de							
Home / Ldap Servers			Danteouris -				
Ldap Servers			# ?				
Name		?	7 About				
Org ID	Default Organisation	?	Cpen-Aud/T can be configured to use LDAP servers (Microsoft Active Directory and/or OperLDAP) to authenticate a user and in additors, to oreade a user account using assigned roles and orgs based on LDAP group membership				
Description		?	? For more detailed information, check the Open-AudT Knowledge Base.				
Domain	your.domain.com	?	7 Notes				
Host	192.168.1.100	?	? If using Active Directory, you do not need to populate the user_dm of user_membership_attribute officiency. These are used by Oracle DRB active				
Port	389	?	? If the user logging on to Open-AudT does not have the access to search LDAP, you can use another account				
Use Secure (LDAPS)	No -	?	? which does have this access. Use the idn_acceunt and idn_paravered to configure this.				
Version	3	?	? Examples				
Use LDAP for Authentication	Yes	?	? Understandig of the second secon				
Use LDAP for Roles	Yes	?	Orusemame and @domain will be replaced by the login details provided by your user on the login page.				
Туре	Active Directory -	?	rycu need to contrgure Advice Lincodry access, you can usually use the example of condisers, donyour, dondamin, doncen for your base_dh, here is no need to set user_dh.				
Base DN	ot=Users, do=your, do=domain, do=com	?	? These are only examples. You may need to adjust these attributes to suit your particular LDAP.				
User DN	on=@usemame,ou=people	?	7				
User Membership Attribute	memberUld	?	7				
Refresh	24	?	7				
Language	English	?	9				
DN Account	on=Administrator, cn=Users, do=your, dc=domain, do=com (if required)	?	7				
DN Password	Your DN Account password (if required)	?	7				
	Submit						

View a LDAP Server Details

Go to menu: Admin -> Ldap Servers-> List Ldap Servers.

You will see a list of Ldap Servers. You can view the details of a Ldap Server by clicking on the blue view icon.

You can also edit or delete the entry.

Hour du do parte La parte La parte La parte </th <th>L Open-AudiT Enterprise 3.3.0 View - Discover - Report - Manage -</th> <th>Admin - Help - Modules -</th> <th>Licenses 👻 🚨 User: admin 👻</th>	L Open-AudiT Enterprise 3.3.0 View - Discover - Report - Manage -	Admin - Help - Modules -	Licenses 👻 🚨 User: admin 👻			
Ldg Servers I I I I I I I I I I I I I I I I I I I	Home / Ldap Servers		Dashboards 🕶			
Image: Strate in the strate	Ldap Servers		₫ • † ?			
Details Name Organisation Description Default Language Host Domain Default Default My Business Default Organisation en 192.168.1.10 yourdomain.com En Showing 1 to 1 of 1 entries First Previous Net Entries First Previous Net Last	50 - records par page		Search:			
My Busines Default Organisation en 192:168.1.0 yourdomain.com Image: Comparisation Showing 1b 1 of 1 entries First Provious Not. Last	Details Name A Organisation Description Default Language Host	0 Domain	Delete			
Showing 1 to 1 of 1 entries First Previous Next Last	 My Business Default Organisation en 192.168.1.10 	yourdomain.com	8			
Conc.AudT Enternate 0.0 is isomed to Connected for 12466 Nodes - Commencial - Exercise 18-Sec-2020	Showing 1 to 1 of 1 entries	F	irst Previous Next Last			
Oper-AudT Enternate 0.0 is isomer to Connected for 12466 Nodes - Commercial - Exercise 18-Sec-2020						
Open-AudT Enternate 0.0 is isomeral to Connected for 12466 Nodes - Commercial - Exercise 18-Sec-2020						
Open-Aut/IT Enterrotes 3.0.0 is lowned to Competitive for 12446 Nodes - Commencial - Exerce 18-Sec-2020						
Open-Aut/IT Enterrotes 3.0.0 is lowned to Competitive for 12445 Nodes - Commencial - Exerce 18-Sec-2020 Present by Competitive						
Onen-AutlT Enterrotes 3.0.0 is licensed to Companie's for 12465 Notes - Commercial - Exercise 18-Sec-2020						
Onen-AutlT Enterrote 3.0.0 is licensed to Compatible for 12946 Nodes - Commercial - Exercise 18-Sec-2020 Present by Compatible						
Onen-Autil TEnterrote 3.0.0 is licensed to Connential for 12465 Nodes - Commercial - Exerce 19-Sec-2020 Present by Connentek						
Open-AudiT Enterrotes 3.0.0 is licensed to Connectek for 12465 Nodes - Commercial - Expires 18-Sec-2020 Powered by Connectek						
Open-AudiT Enterprise 3.0.0 is licensed to Opmantek for 12345 Nodes - Commercial - Expires 18-Sec-2020						
Purchase a license for more nodes by clicking here.	Open-AudiT Enterprise 3.0.0 is licensed to Opmantek for 12345 Nodes - Commercial - Expires 18-Sep-2020 Purchase a license for more nodes by clicking here.					

Database Schema

The database schema can be found in the application is the user has database::read permission by going to menu: Admin -> Database -> List Tables, then clicking on the details button for the table.

API / Web Access

You can access the collection using the normal Open-AudIT JSON based API. Just like any other collection. Please see The Open-AudIT API documentation for further details.