

Troubleshooting

- [Problems Starting Your First Audit](#)
- [Limited Data Returning From Audit](#)
- [Duplicate Devices, Missing Devices, and Devices Being Overwritten](#)
- [Discovery Stopped Working](#)
- [User attempted to view a resource which does not exist error](#)
- [Problems with a runaway queue](#)

The device discovery and auditing function of Open-Audit is designed to work "out of the box" as much as possible with the default settings. However, each user's environment is different and sometimes adjustments to Open-Audit's configuration, network security settings, or credential sets need to be completed in order for accurate audits to complete.

This guide will walk you through troubleshooting the most common problems reported by Open-Audit users.

Problems Starting Your First Audit

If you are having trouble getting your first audit started, it is best to attempt to audit a single, known machine with proper credentials before moving on to full subnets of devices. Start with this guide below on how to audit a single machine.

First, make sure you've configured your devices properly: [Target Client Configuration](#)

Next, disable Blessed Subnets to test if this security feature is inhibiting the audit from running or adding a device to the dB: [Blessed Subnets](#)

Finally, run a discovery on a single device (not on a subnet) to help identify and focus troubleshooting efforts: [How to discover a single Device](#)

Limited Data Returning From Audit

Please read through all of these steps *first*, then return back to the top and complete them one at a time.


Step 1 - First, determine if a detailed audit is being completed or only the initial results of the NMAP scan. The easiest way to do this is to run a Device report; select Report -> Hardware -> Device from the Open-Audit menu, then select the device by clicking the blue View button in the left-hand column of the report. This will display the Device Details screen.

Step 2 - Now, click Details from the menu on the left under Summary. This will open the Details on the right side under the Summary panel. You should look for the Last Seen By field, depending on the version of Open-Audit and type of device this may include NMAP, SNMP, or Audit. If it says NMAP, as the screen shot below, then a full audit has not been completed on this device. The next steps is to determine required ports are open, then if any of the supplied credential set(s) were accepted by the device.

The screenshot displays the Open-Audit web interface. On the left is a sidebar with a 'Summary' section containing links like Summary, Details, Credentials, Purchase, Location, Owned By, Fields, Opmantek Details, Attachments, Cell Details, Audit Log, Change Log, Edit Log, IP Addresses, Settings, and Applications. A red arrow points to the 'Details' link. The main area is titled 'Summary - ip-192-168-88-2' and is divided into two panels. The top panel shows basic information: Name (ip-192-168-88-2), IP (192.168.88.2), Type (Unknown), Description, OS Family, Status (Production), Environment (Production), Manufacturer, Model, and Serial. The bottom panel, titled 'Details', shows more information: Hostname (ip-192-168-88-2), Domain (us-west-1.compute.internal), Dns Hostname (ip-192-168-88-2), Dns Domain (us-west-1.compute.internal), FQDN (ip-192-168-88-2.us-west-1.compute.internal), Class (Desktop), Function, OS Group, OS Name, Form Factor, Uptime, OS Install Date (2000-01-01), Snmp OID, Last Seen (2018-04-30 02:32:50), Last Seen By (nmap), Cluster Name, VM Server Name, VM Group, and Manage in OAE (Yes). A red arrow points to the 'Last Seen By' field, which contains the value 'nmap'.

Step 3 - Before continuing you should increase the log-level and rerun the audit on the device. This will give you in-depth debugging information that will help you determine exactly what went wrong during the audit. To adjust the log_level select Admin -> Configuration -> All from the Open-Audit menu. Find the entry for log_level, which defaults to 5, and increase it to 7. This change will take effect immediately and detailed debug information will be captured during the next audit.

Step 4 - Now that you have adjusted the log_level to 7 and re-run an audit on the device you need to check the Discovery Log to see what happened. First, return to the Device Details screen as you did in Step 1 above. Then, select Discovery Log from the menu on the left. The discovery log, along with other logs and information open up below the Summary panel.



The screenshot shows the 'Discovery Log' window with a search bar and a table of log entries. The table has columns for ID, Timestamp, File, Function, and Message. The entries show the process of discovering a device at 192.168.13.7, including finding the system, testing SSH credentials, and starting the SSH audit.

ID	Timestamp	File	Function	Message
5300	2017-09-26 12:39:59	input	discoveries	Received data for 192.168.13.7, now starting to process
5301	2017-09-26 12:39:59	m_device	find_system	Could not find a match for the device with IP 192.168.13.7
5302	2017-09-26 12:39:59	input	discoveries	WMI Status is false on 192.168.13.7
5303	2017-09-26 12:39:59	input	discoveries	SSH Status is true on 192.168.13.7
5304	2017-09-26 12:39:59	input	discoveries	SNMP Status is false on 192.168.13.7
5305	2017-09-26 12:39:59	include_input_discoveries	discoveries	Testing SSH credentials for 192.168.13.7
5306	2017-09-26 12:39:59	ssh_helper	ssh_credentials	SSH credentials starting
5307	2017-09-26 12:40:00	ssh_helper	ssh_command	SSH command
5308	2017-09-26 12:40:00	ssh_helper	ssh_command	SSH credentials complete. Credential set (using root) named root working on 192.168.13.7
5309	2017-09-26 12:40:00	ssh_helper	ssh_audit	SSH audit starting

As shown in the image above, this example is using SSH credential set. SSH is typically used on Linux devices, WMI is used by Windows machines, and SNMP is used for network devices, Linux and Windows devices. More information on credentials and configuration can be found here: [Target Client Configuration](#). The first underline in the image above is showing that SSH Status suggesting the SSH port is open. Notice WMI Status is shown as false as well as SNMP, if a device was using those forms of credentials then the Status should be true.

Ensure which ever credential type you are using is displaying the Status as true, otherwise the audit will not successfully complete. The second underlined part of this image is confirming that the credential set is working for this device and then continues below to show that the SSH audit is starting. Check the discovery log for this information after auditing your device to see if the credentials are being accepted with no issues.

Step 5 - What if you've done all this and the audit just never seems to find a device at an IP address you know is legitimate?

If you run a discovery and, for whatever reason, Open-Audit doesn't add the device to the database there wont be a direct way to view the Discovery log (Step 4 above). However, there will still be entries in the discovery_log table, you'll just need to dig them out the the database to look through them. To export the discovery logs select Admin -> Database -> List Tables from the Open-Audit menu, then look for the discovery_log table. Click the blue details icon to access the table, then click Export to CSV. This should create a CSV file that can be opened in a text editor or Excel. Search for the device's IP address and look through the related entries to determine what Open-Audit found and what decisions it made regarding the device.

Step 6 - The Device is in the Discovery_log, but the audit ends right after the port check

Open-Audit runs an Nmap discovery on each target IP address. Open-Audit scans the Nmap top 1000 TCP ports, as well as UDP 62078 (Apple IOS) and UDP 161 (SNMP). For Open-Audit to consider a target IP to have a device responding, any of the Nmap Top 1000 TCP Ports must be responding or the UDP 62078.

At this point we need to double-check the information NMAP is receiving from the device. Open a command/terminal window on the Open-Audit server and execute this command (The -F argument is a fast scan of the first 100 ports of the device, the ip_of_device is the IP address or FQDN of the device not responding) -

nmap -F ip_of_device

Example Output

```
[root@myserver:~]# nmap -F 192.168.0.10

Starting Nmap 7.40 ( https://nmap.org ) at 2018-10-16 13:27 UTC
Nmap scan report for targetdevice (192.168.0.10)
Host is up (0.18s latency).
Not shown: 94 closed ports
PORT      STATE SERVICE
22/tcp    open  ssh
80/tcp    open  http
111/tcp   open  rpcbind
443/tcp   open  https
514/tcp   open  shell
3306/tcp  open  mysql
```

If the NMAP scan returns NO OPEN PORTS then the problem is configuration of the target device.

Step 7 - NMAP port scan reports all ports closed for TCP

The next test is to determine if UDP/161 (SNMP) is open. The -sU argument sets NMAP for UDP, and the -p sets scanning for port 161 only, the ip_of_device is the IP address or FQDN of the device not responding.

nmap -sU -p 161 ip_of_device

Test UDP/161

```
[root@myserver:~](255)# nmap -sU -p 161 192.168.0.10

Starting Nmap 7.40 ( https://nmap.org ) at 2018-10-19 13:59 UTC
Nmap scan report for targetdevice (192.168.0.10)
Host is up (0.18s latency).
PORT      STATE SERVICE
161/udp    open  snmp

Nmap done: 1 IP address (1 host up) scanned in 0.55 seconds
```

A target that responds to UDP 161 (SNMP) only and NO other ports (TCP or UDP 62078 / 161) is **not considered to be responding**.

Why do we not consider a UDP port 161 response enough? Because it is very common for firewalls separating network segments to respond with UDP 161 for a target IP regardless of there being an actual device present at that IP address.



UDP port 161 Workaround

OA needs to see more than just UDP port 161 open on a device to consider it a legitimate device. If OA is only seeing UDP port 161 open OA will consider it a false positive and move on. If this is your situation you can edit the /usr/local/open-audit/other/discover_subnet.sh file and set consider_161_enough to "y"

Duplicate Devices, Missing Devices, and Devices Being Overwritten

When Open-AuditIT receives data about a device, either by discovering the device during an audit run or by the user importing the device, it must determine if this discovered device matches a device that already exists within its database, or if it is a new device that should be added. Open-AuditIT uses a series of twelve property matches to determine this.

The Match Rules work as OR comparisons, not AND. This means the first rule that matches a field in the discovered device to one in the dB resolves as an existing device. All Matching Rules have to fail in order for a device to be new and result in a new record being created. If any of these properties do not match, then a new device entry will be created, which could result in duplicate device entries. In situations where properties are duplicated, for example a dbus_id is copied during a VM clone, then an existing device may incorrectly get overwritten/updated rather than a new entry being created resulting in missing devices.

You can check the Discovery Log (see Step 4 above) for your device to see which field was matched on.

Guides for adjusting the matching rules are covered in detail HERE: [Matching Devices](#)

Discovery Stopped Working

If you are running a RedHat or CentOS system and you have upgraded Nmap or went to a previous version sometimes it is necessary to reset the SUID on the binary. You can do this by running the following command:

```
chmod u+s /usr/bin/nmap
```

User attempted to view a resource which does not exist error

A user attempted to view a resource which does not exist.



This notification typically occurs when discovering a single device. When a single device discovery is completed Open-AuditIT automatically deletes the discovery. If the page is refreshed Open-AuditIT wont have a resource to load, and will return you to the Dashboard with this error.

Your first step should be to check and see if the device was audited and added (or updated) in Open-AuditIT. If the device was not found or updated you should check the discovery logs to determine why. To check the discovery logs in Open-AuditIT navigate to menu -> Admin -> Database -> List Tables and look for discovery_log and click the blue details icon next to it. At this point export the file to CSV and you should be able to find your device entry there.

Problems with a runaway queue

If you are here from an in-application link, it is because the last `discovery_log` was more than 1 hour ago, but there is a count in the number of running queue items. This may mean the queue process has hung. You can restart Apache to resolve this (see below to restart Apache). Any queue items currently being processed when this is done will be deleted. Other items in the queue will wait for processing to begin again (see below to start the queue).

View the number of jobs in the queue

```
mysql -u openaudit -popenauditpassword openaudit -e "SELECT COUNT(id) FROM queue;"
```

Delete the remaining items from the queue

```
mysql -u openaudit -popenauditpassword openaudit -e "DELETE FROM queue;"
```

Reset the queue count

```
mysql -u openaudit -popenauditpassword openaudit -e "UPDATE configuration SET value = 0 WHERE name = 'queue_count';"
```

Restart Apache

Restart Apache to kill the running processes (or you should be able to wait for them to complete, your call).

```
sudo service httpd restart
```

Start the Queue Processing

To start the queue being processed (automatically done if you execute a discovery), in a browser, call the below URL (substituting your server name).

You should only have to do this if you manually restart Apache and have items in your queue to be processed.

```
http://YOUR_SERVER/open-audit/index.php/util/queue
```