NMIS - Optimize nmis8/var For Speed - RAM Disk

- Overview
 Procedure
- Procedure
 - Step #1 Determine Space Required
 - Step #2 Create the RAM disk
 - Step #3 Disable NMIS
 - Step #4 Point nmis8/var at the RAM Disk
 - Step #5 Re-enable NMIS
 - Step #6 Verify

Overview

Some customers may benefit by moving files that NMIS reads/writes to very often to a RAM Disk. We have seen this improve performance on pollers that have shared storage and 2,000+ nodes provisioned. The concept is that NMIS will be able to read/write to RAM faster than the shared storage. Most of the files that NMIS touches very often are found in the nmis8/var directory.



Procedure

Step #1 - Determine Space Required

There are two questions that quickly come to mind:

- How big should the RAM disk be?
- How much RAM is available?

Check how much space nmis8/var is currently using; minus the nmis8/var/events directory. We will keep the nmis8/var/events directory on a hard drive because it contains stateful event history; we don't want to loose these if the server is rebooted.

```
[root@TEST var]# pwd
/usr/local/nmis8/var
[root@TEST var]# du -hs
2.6G .
[root@TEST events]# pwd
/usr/local/nmis8/var/events
[root@TEST events]# du -hs
1.7G .
```

In this example we notice that the nmis8/var directory minus the nmis8/var/events directory is approximately 900MB. It appears that a RAM disk of 1GB would be sufficient.

How much RAM is available?

[root@TEST events]# free						
	total	used	free	shared	buffers	cached
Mem:	37016616	25990916	11025700	1796	861860	15379752
-/+ buffers/cache:		9749304	27267312			
Swap:	4169724	558624	3611100			

In the example above there appears to be 11GB of RAM available.

0

The NMIS Self Test settings may need to be adjusted if the nmis8/var directory is running at a high rate of usage. Look for the following attributes in nmis8/conf/Config.nmis:

- 'selftest_min_diskfree_percent' => 10
- 'selftest_min_diskfree_mb' => 25

Step #2 - Create the RAM disk

The RAM disk mount point will need to be created. In this example we are using /media/ramdisk; be sure to mind the permissions.

The following commands will create the RAM disk, keep events on the hard drive, and ensure permissions are not lost. These commands should also need to be added to a script that runs at boot time. On Centos 6 /etc/rc.d/rc.local works well.

mount -t tmpfs -o size=1000M tmpfs /media/ramdisk/
mkdir -p /media/ramdisk/nmis8/var
ln -s /data/nmis8/var/events /media/ramdisk/nmis8/var
/usr/local/nmis8/admin/fixperms.pl

When creating the RAM disk the size parameter may be a number expressed with the suffix k, m or g (kilo, mega, and giga). It may also be expressed with the % sign. For example if you'd like to allow the ramdisk to consume up to 25 percent of the available RAM the following technique could be used.

mount -t tmpfs -o size=25% tmpfs /media/ramdisk

Keep in mind that the ramdisk will not immediately consume the amount of RAM specified. This is the most it will be allowed to consume should it need to. Also keep in mind that if the RAM is oversubscribed the ramdisk could be pushed into swap. If the ramdisk find's itself in swap space it defeats the purpose of this expedition, so do try to avoid this situation.

(1) If you find yourself in a situation where you need to resize the ramdisk on the fly the following method may be useful.

mount -o remount,size=4096M /media/ramdisk

This does not require a reboot and will preserve the files that reside on the ramdisk.

Use the df command to confirm that the ramdisk was created.

```
[root@TEST]# df -h
                  Size Used Avail Use% Mounted on
Filesvstem
/dev/mapper/vg_nmis64-lv_root
                   16G 11G 4.1G 73% /
                   5.9G
                         0 5.9G 0%/dev/shm
tmpfs
/dev/sda1
                  477M 75M 377M 17% /boot
/dev/mapper/vg_nmis64_data-lv_data
                   246G 95G 139G 41% /data
/dev/mapper/vg_nmis64-lv_var
                   20G 10G 8.3G 55% /var
                  1000M 30M 971M 3% /media/ramdisk
tmpfs
```

Step #3 - Disable NMIS

We need to disable NMIS so that it will not attempt to modify the files as we point nmis8/var to the new RAM disk. This is easily accomplished by placing a file called 'NMIS_IS_LOCKED' in the nmis8/conf directly as in the following example.

[root@TEST]# touch /usr/local/nmis8/conf/NMIS_IS_LOCKED

Once the lock file is in place check the server for any nmis.pl processes.

[root@TEST]# ps -ef | grep nmis.pl

When none are found continue

Step #4 - Point nmis8/var at the RAM Disk

Since we are planning to put a sym link in /usr/local/nmis8/ for /var pointing at the new RAM disk; verify that in /usr/local/nmis8/conf/Config.nmis nmis8/var points to /usr/local/nmis8/var. Here's a sample of the directories configuration in that file.

/usr/local/nmis8/conf/Config.nmis

```
'directories' => {
  '<menu_base>' => '<nmis_base>/menu',
  '<nmis_admin>' => '<nmis_base>/admin',
  '<nmis_backups>' => '<nmis_data>/backups',
  '<nmis_base>' => '/usr/local/nmis8',
  '<nmis_bin>' => '<nmis_base>/bin',
  '<nmis_cgi>' => '<nmis_base>/cgi-bin',
  '<nmis_conf>' => '<nmis_base>/conf',
  '<nmis_data>' => '<nmis_base>',
  '<nmis_logs>' => '<nmis_base>/logs',
  '<nmis_menu>' => '<nmis_base>/menu',
  '<nmis_models>' => '<nmis_base>/models',
  '<nmis_var>' => '<nmis_data>/var',
  'config_logs' => '<nmis_logs>/config',
  'database_root' => '<nmis_data>/database',
  'json_logs' => '<nmis_logs>/json',
  'log_root' => '<nmis_logs>',
  'mib_root' => '<nmis_base>/mibs',
  'plugin_root' => '<nmis_conf>/plugins',
  'report_root' => '<nmis_base>/htdocs/reports',
  'script_root' => '<nmis_conf>/scripts',
  'web_root' => '<nmis_base>/htdocs'
},
```

Create the sym link in /usr/local/nmis8/ sending /var to the RAM disk.

```
ln -s /media/ramdisk/nmis8/var/ /usr/local/nmis8
```

Step #5 - Re-enable NMIS

Remove the previously created NMIS lock file.

```
[root@TEST]# rm /usr/local/nmis8/conf/NMIS_IS_LOCKED
```

Step #6 - Verify

• move to the /usr/local/nmis8/var directory and execute a 'df -h .' command. This command should reveal that we are indeed on the ramdisk.

```
[root@TEST ~]# cd /usr/local/nmis8/var
[root@TEST var]# df -h .
Filesystem Size Used Avail Use% Mounted on
tmpfs 1000M 30M 971M 3% /media/ramdisk
[root@TEST var]#
```

- Take a look in the /usr/local/nmis8/var directory and confirm that node.json and view.json files have been created.
- Verify that the NMIS GUI is functioning normally.
- Review the nmis8/logs/nmis.log file
- Check the root user mailbox