

Default Credentials (Passwords) for NMIS8 and NMIS9 VMs

- [Open-Audit Default Credentials](#)
- [Default Credentials for the NMIS8 and NMIS9 VMs'](#)
 - [Shell/Console Access, SSH](#)
 - [NMIS Web Users](#)
 - [NMIS8 Specific](#)
 - [Open-Audit Web Users](#)
 - [MySQL root user for Database](#)
 - [Changing the Credentials](#)
 - [Console/System](#)
 - [Web](#)
- [Default Credentials for the NMIS4 VM](#)

Open-Audit Default Credentials

If you are looking for default credentials for Open-Audit, you can find them @ [Information about default users and passwords](#)

Default Credentials for the NMIS8 and NMIS9 VMs'

Shell/Console Access, SSH

Please note: this is for logging in to the the virtual appliance interactively, i.e. on your VM console or via SSH. This is *not* the password for the Web GUI!

- Console access: User `root`, password `NM1$88`
- SSH access: User: `omkadmin` password: `NM1$88`
 - **The VM has been configured with the Linux best practice of not allowing direct access to root. Once you have authenticated as another user you can elevate your privileges using `sudo` or `su`.**
- Only in VM releases before May 2017: user `nmis`, password `NM1$88`.
In newer releases the `nmis` shell account is locked. To restore this access you can run `passwd nmis` when logged in as `root`.

NMIS Web Users

These are the passwords for the NMIS Web GUI, which won't work for the VM console or SSH.

- `nmis/nm1888`
- `admin/password`
- (VM Appliances before 8.6.0G: `nmisadm/nm1888`)

NMIS8 Specific

- **Open-Audit Web Users**
 - `admin/password`
- **MySQL root user for Database**
 - This password is not stored. It is only used to setup the initial Open-Audit database and can be changed directly in MySQL.
`root/openauditrootuserpassword`

Changing the Credentials

Console/System

To change the Console passwords, either login as the user in question and run the `passwd` command, or login as (or become) the superuser and run `passwd otheruser`.

```
# to change the current user's password (which you might want to check by running "id" first)
passwd
# to change the nmis user password, if you're the superuser
passwd nmis
```

Web

If you have not changed the NMIS Authentication configuration, it will be using the default method which are users defined in a file managed with `htpasswd`.

In all VM Appliance releases since 2015 the `htpasswd` file is shared between NMIS and the Opmantek applications (except Open-Audit Community).

The default installation location for NMIS is `/usr/local/nmis8` (it may be installed somewhere else, adjust the commands accordingly).

To update the password for web user *SOMEUSER*, run the following commands as user `nmis` or root:

```
cd /usr/local/nmis8/conf
# use crypt for hashing
htpasswd -d users.dat SOMEUSER
# use apache-specific md5 for hashing, and only for NMIS after 8.5G
htpasswd -m users.dat SOMEUSER
```

Important: in versions up to and including 8.5G, NMIS only supports crypt as password hashing method. Depending on your operating system your `htpasswd` program may default to the MD5 method and in that case you must include the `-d` argument as shown above.

Further info regarding authentication and user management can be found on the [User Management in NMIS8](#) page.

Default Credentials for the NMIS4 VM

Start the VM, and Centos V4 should boot to a login screen.

Login as root, the password is documented on the VM Description tab.

Username: root

Password administrator

Username: nmis

Password: nmis@nmis

Related Topics

- [Opmantek NMIS8 Virtual Appliance: Release Notes](#)
- [Opmantek NMIS9 Virtual Appliance: Release Notes](#)
- [Opmantek Virtual Appliance: Installation and Getting Started](#)
- [Virtual Appliance Maintenance: Updating Software](#)
- [Enabling DNS Server on Opmantek NMIS8 VM](#)